



# File check with [teamwork-net|de]

## **Preflight Manager**


The recent update has made our Internet portal *teamwork-net* even **more comfortable**. The current version provides a **new**, **free service** to our customers.

The PDF-files you deliver via the portal are **automatically checked** according to their printing requirements. In case of errors, you will receive the **preflight report** via e-mail.





The page survey shows at a glance which pages contain errors (red symbol) or warnings (yellow symbol) or are technically correct (green symbol).



If you have activated the Preflight – Manager, the page survey shows you a listing of the detected errors.

## List of the most frequent error messages

In order to enable the delivery of errorless files by means of the Preflight Manager, the most frequent error messages are explained in the list below.

# 😣 Error

**Document is damaged. Some objects may be missing.** Damaged documents cannot be processed.

Document has PDF encryption.Document security printing is not allowed.Document security editing content is not allowed.Encrypted documents or documents with security settings cannot be processed.

#### **Detected annotation that is set to print.** Annotations on the print format cause an unwanted printout.

Font is not embedded. Not embedded fonts cannot be processed.



**Spot color is used.** The conversion of spot colors will cause changes in terms of color.

Color Space RGB is used. Color Space CalGrey is used. Color Space CalGrey is used. Color Space Lab is used. Color Space ICC-based is used. Image element is tagged with an ICC profile. Text/Lineart element is tagged with an ICC profile. The conversion of color spaces, which are not CMYK, will cause changes in terms of color.

Resolution of color/grayscale image is below 150 dpi. Resolution of monochrome image is below 600 dpi.

A low resolution of color/grayscale images or monochrome images causes a low print quality.

### **OPI image is used.** The use of OPI-information with images may cause differences in position and resolution.

**Detected Layers.** The use of layers may cause unwanted effects when combining the layers.

#### Detected transparent element.

The processing of transparent elements may cause unwanted effects.

# Information

The listings of this category only provide information about the work process.